

Connect to your EC2 Windows instance โดย Fleet Manager

การใช้ Fleet Manager ใน AWS Systems Manager เพื่อเชื่อมต่อกับ Windows Instance เป็นวิธีที่ช่วยให้คุณจัดการ Server Windows EC2 ได้โดยตรงผ่าน AWS Management Console โดยไม่ต้องใช้ RDP หรือ Bastion Host


ข้อกำหนดเบื้องต้น

1. เปิดใช้งาน AWS Systems Manager Agent (SSM Agent)

- ตรวจสอบว่า EC2 Instance ติดตั้งและเปิดใช้งาน SSM Agent:
 - Get-Service AmazonSSMAgent

2. Instance Profile (IAM Role)

- EC2 Instance ต้องมี IAM Role ที่แนบ Policy ดังนี้:
 - AmazonSSMManagedInstanceCore
- สามารถเพิ่ม Role ได้ผ่าน AWS Console:
 - EC2 Dashboard > เลือก Instance > Actions > Security > Modify IAM Role




3. เปิดใช้งาน Fleet Manager

- ไปที่ Systems Manager > Fleet Manager
- ตรวจสอบว่า Instance ถูกจัดการโดย Systems Manager และปรากฏใน Fleet Manager
-

วิธีการ Connect Windows Instance ผ่าน Fleet Manager

1. ไปที่ AWS Console


- EC2 Dashboard > เลือก **Connect**
- ส่วน Connection type > เลือก **Connect using Fleet Manager**
- คลิก **Fleet Manager Remote Desktop**



The screenshot shows the AWS Management Console interface for connecting to an EC2 instance. The top navigation bar includes 'Instances (1/1)', 'Connect', 'Instance state', 'Actions', and 'Launch instances'. The instance list shows 'Demo-Fleet-Manager' with ID 'i-06ccec0fff7a5d305' in a 'Running' state. The 'Connect to instance' page is displayed, showing the 'RDP client' tab. Under 'Connection Type', 'Connect using Fleet Manager' is selected. The 'Username' is set to 'Administrator'. A 'Fleet Manager Remote Desktop' button is visible. A note at the bottom states: 'If you've joined your instance to a directory, you can use your directory credentials to connect to your instance.'

2. เปิด Remote Desktop Session

- เลือก Authentication type
 - **User Credentials:** กรอก User / Password



The screenshot shows the 'Demo-Fleet-Manager' Remote Desktop Session authentication dialog. It has a 'Close' button in the top right. Under 'Authentication type', 'User credentials' is selected. The 'Username' field contains 'administrator'. The 'Password' field is masked with dots. There is a 'Show password' checkbox. A 'Connect' button is in the bottom right corner.

- Key Pair: Browse your key pair

Demo-Fleet-Manager
i-06ccce0ff7a5d305

Close

Authentication type
The type of authentication to use when connecting to the node. [Learn more](#)

☐ User credentials
Username and password.

☒ Key pair
Connect as Administrator using EC2 key pair.

Administrator account name
The default administrator account name might vary based on your locale.

Administrator

Key pair
Key pair associated with the instance
TOR

Key pair content
Select a method for uploading the key pair content.

☒ Browse your local machine to select the key pair file.
The private key file content is automatically uploaded to your browser.

☐ Paste key pair content
Copy and paste the key pair content into the field below.

Must be an RSA key pair.

TOR.pem

Connect

3. ยืนยันและเริ่ม Session

- Fleet Manager จะสร้าง Remote Desktop Session ให้คุณเชื่อมต่อ

